

PS 1000-B / PS 1000 / PSA 100

HOW TO UPDATE YOUR SOFTWARE.



Overall Process

1. Check the software version on your tool
2. Confirm that there is a new software-update available
3. Download the update to the PROFIS X-Scan PS 1000 software on your desktop
4. Copy the update onto a USB drive and install on the tool itself

Short Questions and Answers


- **Why update?** – Software updates can provide new functionality or improvements. New features in desktop software often require an update on the tool itself for most effective use.
- **Can I update my PS 1000-B?** – Yes, however there will not be new features. The PS 1000-B is a basic option without advanced capabilities like connecting to desktop software and so forth.

Check the software version of the tool

<p>Step 1</p> <p>1 Turn tool ON</p> <p>2 Press "Settings"</p>	<p>Step 2</p> <p>3 Scroll to "Info"</p> <p>4 Push "OK"</p>
<p>Step 3</p> <p>5 Note the "Update Package" number</p>	<p>For PSA 100 Monitor: Same process</p> <p>5 Note the "Update Package" number</p>


Check if there is a new software update available and update the tool

Step 1



- Connect to the internet
- Download and install PROFIS PS 1000 X-Scan Software
- Start the PROFIS PS 1000 X-Scan Software
- Click on “?”, then select “Information...”

Step 2



1. Information window will pop up, select the “Update PS 1000 / PSA 100” tab.
2. Select “Check for update now”
3. Verify that a newer update is available (higher number than the one on your desktop or the tool)
4. If an update is available, the “Download update” button becomes available. Select and download (250-300 MB)
5. Once the software download is complete, “Prepare USB stick for PS 1000 / PSA 100” becomes available.
6. Put an empty USB stick into the USB port of your computer, select the button and follow the prompts.
7. The update will then be copied onto the USB drive (zip folder is added to the drive)

Note: Use a “USB 2 compatible” USB drive or the original Hilti PSA 97 Data Module. Ensure that the USB drive is blank before loading the software onto it. (Update has to be the ONLY file on the drive.)

Step 3



- Make sure the tool is OFF and the battery is fully charged
- Insert the USB drive into the USB port of the applicable tool
- Turn the tool ON, the tool will then initiate the update
- Go through possible update cycles (restart) until the tool tells you to remove the USB stick
- Go through Set-Up Settings (update may reset to metric)
- Verify the software version on the tool to confirm that the update was successful

For more information

Hilti Advanced Layout & Detection Support: 918-872-3551

Hilti. Outperform. Outlast.

Hilti, Inc. (U.S.) | 1-800-879-8000 | en español 1-800-879-5000 | www.us.hilti.com | Hilti (Canada) Corp. | 1-800-363-4458 | www.hilti.ca

